

1. Camera driver tutorial

1. Camera driver tutorial

1.1 Common API functions in camera drivers

1.1.2. cv2.VideoCapture() function:

1.1.3. cap.set() function

1.1.3. cap.isOpened() function:

1.1.4. ret,frame = cap.read() function:

1.1.5. cv2.waitKey() function:

1.1.6. cap.release() and destroyAllWindows() functions:

1.2 Implementation effect

1.1 Common API functions in camera drivers

1.1.2. cv2.VideoCapture() function:

```
cap = cv2.VideoCapture(0)
```

The parameter in VideoCapture() is 0, which means Raspberry Pi video0.

(Note: You can view the camera through the command `ls /dev/ video*`)

```
cap = cv2.VideoCapture("../1.avi")
```

VideoCapture("../1.avi"), which means that the parameter is the video file path and the video is opened.

1.1.3. cap.set() function

Set camera parameters. Do not modify them at will. Common configuration methods:

```
capture.set(CV_CAP_PROP_FRAME_WIDTH, 1920); #Width
```

```
capture.set(CV_CAP_PROP_FRAME_HEIGHT, 1080); #Height
```

```
capture.set(CV_CAP_PROP_FPS, 30); #Frame rate
```

```
capture.set(CV_CAP_PROP_BRIGHTNESS, 1); #Brightness 1
```

```
capture.set(CV_CAP_PROP_CONTRAST,40); #Contrast 40
```

```
capture.set(CV_CAP_PROP_SATURATION, 50); #Saturation 50
```

```
capture.set(CV_CAP_PROP_HUE, 50); #Hue 50
```

```
capture.set(CV_CAP_PROP_EXPOSURE, 50); #Exposure 50
```

Parameter explanation:

CV_CAP_PROP_POS_MSEC - Current position of the video, in milliseconds or video acquisition timestamp

CV_CAP_PROP_POS_FRAMES - Frame index to be decompressed/acquired in the next step, starting from 0

CV_CAP_PROP_POS_AVG_RATIO - Relative position of the video file (0 - start of the video, 1 - end of the video)

CV_CAP_PROP_FRAME_WIDTH - Frame width in the video stream

CV_CAP_PROP_FRAME_HEIGHT - Frame height in the video stream

CV_CAP_PROP_FPS - Frame rate

CV_CAP_PROP_FOURCC - Four characters representing codec

CV_CAP_PROP_FRAME_COUNT - Total number of frames in the video file

The function `cvGetCaptureProperty` obtains the specified properties of the camera or video file.

The following are detailed parameters:

```
#define CV_CAP_PROP_POS_MSEC 0 //Current position calculated in milliseconds
```

```
#define CV_CAP_PROP_POS_FRAMES 1 //Current position calculated in frames
```

```
#define CV_CAP_PROP_POS_AVI_RATIO 2 //Relative position of the video, from 0 to 1 The first three parameters should be related to video playback and reading related dynamic information
```

```
#define CV_CAP_PROP_FRAME_WIDTH 3 //Frame width
```

```
#define CV_CAP_PROP_FRAME_HEIGHT 4 //Frame height
```

```
#define CV_CAP_PROP_FPS 5 //Frame rate
```

```
#define CV_CAP_PROP_FOURCC 6 //4 character encoding method
```

```
#define CV_CAP_PROP_FRAME_COUNT 7 //Number of video frames
```

```
#define CV_CAP_PROP_FORMAT 8 //Video format
```

```
#define CV_CAP_PROP_MODE 9 //Backend specific value, indicating the current capture mode.
```

```
#define CV_CAP_PROP_BRIGHTNESS 10 //Brightness
```

```
#define CV_CAP_PROP_CONTRAST 11 //Contrast
```

```
#define CV_CAP_PROP_SATURATION 12 //Saturation
```

```
#define CV_CAP_PROP_HUE 13 //Hue
```

```
#define CV_CAP_PROP_GAIN 14 //Gain
```

```
#define CV_CAP_PROP_EXPOSURE 15 //Exposure
```

```
#define CV_CAP_PROP_CONVERT_RGB 16 //Boolean flag whether the image should be converted to RGB.
```

```
#define CV_CAP_PROP_WHITE_BALANCE 17 //White balance
```

```
#define CV_CAP_PROP_RECTIFICATION 18 //Stereo camera correction flag (Note: only supports DC1394 v2.x end currently)
```

1.1.3. `cap.isOpened()` function:

Return true for success, false for failure

1.1.4. `ret, frame = cap.read()` function:

`cap.read()` reads the video frame by frame, `ret, frame` are the two return values of the `cap.read()` method. Among them, `ret` is a Boolean value. If the read frame is correct, it returns `True`. If the file is not read to the end, its return value is `False`.

`frame` is the image of each frame, which is a three-dimensional matrix.

1.1.5. `cv2.waitKey()` function:

The parameter is 1, which means a delay of 1ms to switch to the next frame image. If the parameter is too large, such as `cv2.waitKey(1000)`, it will feel stuck due to the long delay.

The parameter is 0, such as `cv2.waitKey(0)`, which only displays the current frame image, which is equivalent to pausing the video.

1.1.6. `cap.release()` and `destroyAllWindows()` functions:

`cap.release()` releases the video, and calls `destroyAllWindows()` to close all image windows.

1.2 Implementation effect

Source code path:

/home/pi/project_demo/07.AI_Visual_Recognition/01.Camera_Driving/01_Camera_Driving.ipynb

```
import cv2
import ipywidgets.widgets as widgets
import threading
import time

image_widget = widgets.Image(format='jpeg', width=640, height=480) #设置摄像头显示
组件 Set up the camera display component
```

```
#bgr8转jpeg格式 bgr8 to jpeg format
import enum
import cv2

def bgr8_to_jpeg(value, quality=75):
    return bytes(cv2.imencode('.jpg', value)[1])
```

```
image = cv2.VideoCapture(0) #打开摄像头/dev/video0 Open
the camera /dev/video0
width=640
height=480
image.set(cv2.CAP_PROP_FRAME_WIDTH,width)#设置图像宽度 Set the image width
image.set(cv2.CAP_PROP_FRAME_HEIGHT,height)#设置图像高度 Set the image height

# image.set(3,600)
# image.set(4,500)
# image.set(5, 30) #设置帧率 Setting the frame rate
# image.set(cv2.CAP_PROP_FOURCC, cv2.VideoWriter.fourcc('M', 'J', 'P', 'G'))
# image.set(cv2.CAP_PROP_BRIGHTNESS, 40) #设置亮度 -64 - 64 0.0 Set Brightness
-64 - 64 0.0
# image.set(cv2.CAP_PROP_CONTRAST, 50) #设置对比度 -64 - 64 2.0 Set Contrast
-64 - 64 2.0
```

```
# image.set(cv2.CAP_PROP_EXPOSURE, 156) #设置曝光值 1.0 - 5000 156.0 Set the exposure value 1.0 - 5000 156.0
```

```
ret, frame = image.read() #读取摄像头数据 Reading camera data  
image_widget.value = bgr8_to_jpeg(frame)
```

```
try:  
    display(image_widget) #显示摄像头组件 Display camera components  
    while 1:  
        ret, frame = image.read()  
        image_widget.value = bgr8_to_jpeg(frame)  
        time.sleep(0.010)  
except KeyboardInterrupt:  
    print(" Program closed! ")  
    pass
```

#使用完成对象记住释放掉对象，不然下一个程序使用这个对象模块会被占用，导致无法使用
#Remember to release the object after using it, otherwise the object module will be occupied by the next program, making it unusable.
image.release()

```
01_Camera_Driving.ipynb x +  
+ ✂ 📄 ▶ ■ ↺ ⏮ ⏭ Code ▾  
    image_widget.value = bgr8_to_jpeg(frame)  
    time.sleep(0.010)  
except KeyboardInterrupt:  
    print(" Program closed! ")  
    pass
```

